

# Baty Fusion-4.12.6 Release Notes

Hello,

Please see the bullet points below for changes and improvements for Fusion 4.12.6. This update is applicable for all Baty Ventures and VuMasters currently running Mk4 software. The correct update procedure must be followed to ensure the new software will work correctly, this information can be found in the MK4 user guide in Chapter 58, page 164.

## **New Features since version 4.12.4:**

- DXFs can now be imported whilst using comma decimal points.
- You may now construct a surface from a surface.
- When feature predict accepts a feature, it will now make a sound.
- Clicking the engage drives button when your machine isn't referenced will ask you to reference.
- The software will now wait until it has finished referencing before it loads.
- When manually measuring references using DXF to Import an Inspection Template, a new message will appear asking the user to "Please move the machine to a safe area". This message must be cleared before measurements are taken.

## **Main bug fixes including:**

- Improved the quality of the graphic reports when saved using the "Combined Reports" option.

## **Fixes and improvements for just VuMaster MK4:**

- Fixed an error to improve the acceleration and deceleration of the Z axis.

Best Regards,  
Product Development